Operating Systems Architecture, Part IIIc

CS239
Advanced Operating Systems
October 13, 1998
Dr. Richard Guy

Outline

- Part I: Why study OS?
- Part II: Best way to build OS
- Part III: What's new?
  - Microkernels, revisited
  - Operating System Extensibility
  - **64-bit Architectures**
    - The Challenge of Wide Virtual Addresses
    - Opal
    - Anonymous RPC

Part IIIc Source Materials

- 64-bit architectures
  - Opal: A single Address Space System for 64-bit Architectures, by Chase, et al, IEEE WWOS92.
  - Sharing and Protection in a Single Address Space OS, by Chase, et al, ACM TOCS 11/94.
  - Anonymous RPC: Low-Latency Protection in a 64-Bit Address Space, by Yarvin, et al, USENIX, 1993.

Part IIc Sources, continued

- The Expected Lifetime of "Single-Address-Space" Operating Systems, by Kotz and Crow, 1996.

64-Bit Address Space Machines

- An entirely different challenge for operating system architecture
- A fundamental assumption about our hardware is in the process of changing
- Should we change the OS to match it?

The Challenge of Wide Virtual Address Spaces

- When virtual memory was created, 16 or 32 bit addresses spaces were available
- Reasonable size for one process
  - but maybe not for all processes on a machine
  - and certainly not for all processes ever on a machine

Wide Address Space Architectures

- Computer architects can now give us 64 bit virtual addresses
- A 64 bit address space, consumed at 100 megabytes per second, lasts 5000 years
  - orders of magnitude beyond any process' needs
  - 40 bits can address a terabyte
- Lifetime paper has more careful study

Do We Care?

- Should OS designers care about wide address spaces?
- Well, what can we do with them?
- One possible answer
  - put all processes in the same address space
  - maybe all processes for all time?

Traditional Addressing Architectures

- Each process gets its own complete 32-bit address space
- Only that process can correctly "issue" its addresses
- Virtual memory hardware + OS software supports switching of virtual memories for different processes
- IPC must usually go through the OS

Implications of Single Shared Address Space

- IPC is trivial
  - Everybody agrees on the addresses of everything
  - Shared memory, RPC are thus simple
- Separation of concepts of address space and protection domain
- *Uniform-address space*

Address Space and Protection Domain

- A process has a protection domain
  - The data that cannot be touched by other processes
- And an address space
  - The addresses it can generate and access
- In standard systems, these concepts are merged

Separating the Concepts

- These concepts are potentially orthogonal
- Just because you can issue an address doesn't mean you can access it
- (Though clearly to access an address you must be able to issue it)
- Existing hardware can support this separation

Context-Independent Addressing

- Addresses mean the same thing in any execution context
- So a given address always refers to the same piece of data
- Key concept of uniform-address systems
- Allows many OS optimizations and improvements

Uniform-Addressing Allows Easy Sharing

- Any process can issue any address
  - So any data can be shared
- All that's required is changing protection to permit desired sharing
- Suggests programming methods that make wider use of sharing

The Opal System

- New OS using uniform-addressing
- Developed at U. of Washington
- Not intended as slight alteration to existing Unix system
- Other uniform-address operating systems are under development

Protection Mechanisms for Uniform-Addressing

- Protection domains are assigned portions of the address space
- They can allow other protection domains to access them:
  - Read-only
  - With transferable access permissions
  - With system-enforced page-level locking

Program Execution in Uniform-Access Memory

- Executing a program creates a new protection domain
- The new domain is assigned an unused portion of the virtual address space
- But it may also get access to used portions
- E.g., a segment containing the required executable image

Virtual Segments

- Global address space is divided into segments
  - Each composed of variable number of contiguous virtual pages
- Domains can only access segments they *attach* to
- Attempting to access unattached segment causes a segment fault

Persistent Memory in Opal

- *Persistent* segments exist even when attached to no current domain
- *Recoverable* segments are permanently stored
  - And can thus survive crashes
- All Opal segments can be persistent and recoverable
- Pointers can thus live forever on disk

Code Modules in Opal

- Executable code stored in *modules*
  - independent of protection domains
- *Pure modules* can be easily shared
  - essentially static
- Can get benefit of dynamic loading without run-time linking

Address Space Reclamation

- Trivial in non-uniform-address systems
- Tricky in uniform-address systems
- Problem akin to reclaiming inodes in the presence of (multiple) hard links
- But even if segments improperly reclaimed, only trusting domains can be hurt

Anonymous RPC

- Goal: "Build system that combines the protection of UNIX processes and the speed of threads, to make IPC cheap enough for heavy use."
- Problems
  - VM to enforce protection is expensive (more state means slower context switches)
  - lightweight threads are fast, not safe or secure

ARPC main idea

- In very large, sparse address space, VM address mappings can act as capabilities
  - knowledge of address implies permission
  - restricting knowledge provides protection
- Resulting anonymity is basis for general-purpose protection mechanism

ARPC Implementation

- Need way to assign addresses at load time
  - non-discoverable, non-derivable
- So, select addresses randomly
  - only brute-force search can "break" method
  - but, no truly random number generator
  - use cryptosystem (key: some secure password)
    - plaintext is allocation sequence number
    - resulting encrypted text is securely random

Is brute force search feasible?

- Method relies on infeasibility of brute force address probing
  - issue addresses and catch seg-faults
- Key parameters
  - time to process segmentation faults
  - size of physical memory
  - size of virtual address space

"Time to Breach" results

PhysMem	1s delay	1ms delay	1µs delay
16MB	24162 yrs	24 yrs	1.25 wks
256MB	1510 yrs	1.5 yrs	13.2 hrs
2GB	188 yrs	2.3 mo	1.7 hrs
16GB	23 yrs	8.5da	12 mins

Maintaining Anonymity

- RPC path of control must flow through an intermediary
  - protected
  - aware of RPC binding
  - able to manage control and data flow without revealing either's address to the other
  - kernel is obvious, and slow!

Anonymity, continued

- Exploit execute-only page protection
  - caller knows address of callee text, but can't damage text or discover data locations
  - use execute-only jump table which contains the actual service entry point as immediate operand
  - use separate stack during server execution
  - cost of anonymity: one additional jump instr + two stack/register switch/save methods
  - if some trust exists, can reduce some/all saves

Null RPC performance

Protocol	instructions
SRC RPC	1226
Mach RPC	950
LRPC	424
URPC	251
ARPC	116

Meta-level Summary Comments

- When exploring a new paradigm, push it to the (believed) limits
- Try separating joint concepts, or splitting a previously "atomic" idea into multiple parts
- Sometimes OS progress pushes HW progress; sometimes, vice-versa